



To: For Distribution

From: Jud Parker Jud Tarke

SUBJECT: Adding a Local TCP/IP Printer (to avoid Domain Login)

Users who login to the FNAL Domain can setup network printers with no problem; however, people who login to their PC with a <u>local account</u> (i.e. visitors. guests, etc.) will need to setup a local TCP/IP printer port and printer in order to access the Directorate's printers.

The following chart lists the Color and Laser Printers which are located within the Directorate on WH-2 East and West, and in the Public Affairs Office on WH-1 East.

Located Where / Who	Printer Name	Mfg. & Type / Model	IP Address
Public Affairs WH-1E	Color_PubAff	Tektronix 840 Ext	131.225.19.64
Marilyn Smith WH-2E	Color_DirAdm	Tektronix 840 Ext	131.225.19.19
Jud Parker WH-2E	Color_DirSpr	Tektronix 860 DP	131.225.19.9
Phyllis Metelmann WH-2W	Color_InfTec	Tektronix 860 DP	131.225.19.8
Public Affairs WH-1E	WH1E_PubAff	Apple LaserWriter 16/600	131.225.19.23
Michelle Gleason WH-2E	WH2E_DirAdm	HP LaserJet 8100DN	131.225.19.71
Sue Grommes WH-2E	WH2E_FrDesk	HP LaserWriter 4Si Mx	131.225.19.22
Program Planning WH-2E	WH2E_PrgPln	HP LaserWriter 4Si Mx	131.225.19.16
Budget Office WH-2W	WH2W_Budget	HP LaserWriter 5Si Mx	131.225.19.48
Phyllis Metelmann WH-2W	WH2W_InfTec	HP LaserWriter 4Si Mx	131.225.19.51
Xerox Room WH-2E	WH2E_Docutk	Xerox Document Centre 265ST	131.225.19.15


To setup a local TCP/IP printer port and printer:

Go to Start → Settings → Printers → Add Printer







 At the Local or Network Printer window... select Local printer, optionally check Automatically detect and install my Plug and Play printer, and then click Next



At the New Printer Detection window... click Next




• At the Select the Printer Port window... select Create a new port and for Type, choose HP Standard TCP/IP Port (from the drop-down list), and then click Next



At the Welcome to the Add Standard TCP/IP Printer Port Wizard... click Next




 At the Welcome to the Add Port window... type in the printer's IP Address (from the list on the first page), let the Port Name default, and then click Next




• At the Completing the Add Standard TCP/IP Printer Port Wizard... click Finish




 Back at the Add Printer Wizard... select the printer's Manufacturer and then the printer's Type or Model (from the list on the first page), and then click Next




 At the Use Existing Driver window... select Keep Existing Driver (recommended) and then click Next




 At the Name Your Printer window... type in a Printer Name or accept the default, select Yes or No to make the printer your default printer, and then click Next



• At the Printer Sharing window... select Do not share this printer and then click Next




• At the **Print Test Page** window... select **Yes** or **No** to print a test page and confirm the printer's setup and connection, and then click **Next**



• At the Completing the Add Printer Port Wizard window... click Finish



• If you chose to print a test page then you will see a window similar to the following. Assuming that the **Test Page** printed out correctly, click **OK**



• Done!